
ebuildtester Documentation

Release 0.1.35

Nicolas Bock

May 17, 2022

Contents:

1 Requirements	3
2 Usage	5
3 Command line arguments	7

This script is a tool to test a Gentoo ebuild and its dependencies. The idea is that the package is emerged in a clean (and current) stage3 Docker container.

CHAPTER 1

Requirements

You require Docker and FUSE. Docker must be configured to use the devicemapper storage driver. This can be achieved with the following inside /etc/docker/daemon.json:

```
{  
  "storage-driver": "devicemapper"  
}
```


CHAPTER 2

Usage

We are going to assume that the user has a local git clone of the portage tree in

```
/usr/local/git/gentoo
```

We have added a new ebuild and would like to verify that the build dependencies are all correct. We can build the package (ATOM) with:

```
ebuildtester --portage-dir /usr/local/git/gentoo \
--atom ATOM \
--use USE1 USE2
```

where we have specified two USE flags, USE1 and USE2. The *ebuildtester* command will now create a docker container and start installing the ATOM. All specified dependencies will be installed as well.

CHAPTER 3

Command line arguments

The command understands the following command line arguments:

```
usage: ebuildtester [-h] [--version] [--atom ATOM [ATOM ...]] [--binhost BINHOST] [--live-ebuild]
                     [--manual] --portage-dir PORTAGE_DIR [--overlay-dir OVERLAY_DIR] [--update]
                     [--install-basic-packages] [--threads N] [--use USE [USE ...]]
                     [--global-use GLOBAL_USE [GLOBAL_USE ...]] [--unmask ATOM] [--unstable]
                     [--gcc-version VER] [--python-single-target PYTHON_SINGLE_TARGET]
                     [--python-targets PYTHON_TARGETS] [--rm]
                     [--storage-opt STORAGE_OPT [STORAGE_OPT ...]] [--with-X] [--with-vnc]
                     [--profile PROFILE] [--docker-image DOCKER_IMAGE] [--pull]
```

A dockerized approach to test a Gentoo package within a clean stage3.

optional arguments:

-h, --help	show this help message and exit
--version	show program's version number and exit
--atom ATOM [ATOM ...]	The package atom(s) to install
--binhost BINHOST	Binhost URI
--live-ebuild	Unmask the live ebuild of the atom
--manual	Install package manually
--portage-dir PORTAGE_DIR	The local portage directory
--overlay-dir OVERLAY_DIR	Add overlay dir (can be used multiple times)
--update	Update container before installing atom
--install-basic-packages	Install basic packages after container starts
--threads N	Use N (default 8) threads to build packages
--use USE [USE ...]	The use flags for the atom

(continues on next page)

(continued from previous page)

```
--global-use GLOBAL_USE [GLOBAL_USE ...]
    Set global USE flag
--unmask ATOM
    Unmask atom (can be used multiple times)
--unstable
    Globally 'unstable' system, i.e. ~amd64
--gcc-version VER
    Use gcc version VER
--python-single-target PYTHON_SINGLE_TARGET
    Specify a PYTHON_SINGLE_TARGET
--python-targets PYTHON_TARGETS
    Specify a PYTHON_TARGETS
--rm
    Remove container after session is done
--storage-opt STORAGE_OPT [STORAGE_OPT ...]
    Storage driver options for all volumes (same as Docker param)
--with-X
    Globally enable the X USE flag
--with-vnc
    Install VNC server to test graphical applications
--profile PROFILE
    The profile to use (default = default/linux/amd64/17.1)
--docker-image DOCKER_IMAGE
    Specify the docker image to use (default = gentoo/stage3)
--pull
    Download latest docker image
```